-- --

IEEE P1003.2 Draft 11.2 – September 1991

The command:

```
umask -- -w
```

sets the mode mask so that subsequently created files have all their write bits cleared. Note that *mask* operands `-r`, `-w`, `-x`, or anything beginning with a hyphen, must be preceded by `--` to keep it from being interpreted as an option.

History of Decisions Made

The description of the historical utility was modified to allow it to use the symbolic modes of `chmod`. The `-s` option used in earlier drafts was changed to `-S` because `-s` could be confused with a *symbolic_mode* form of mask referring to the S_ISUID and S_ISGID bits.

The default output style is implementation defined to permit implementors to provide migration to the new symbolic style at the time most appropriate to their users. Earlier drafts of this standard specified an `-o` flag to force octal mode output. This was dropped because the octal mode may not be sufficient to specify all of the information that may be present in the file mode creation mask when more secure file access permission checks are implemented.

It has been suggested that trusted systems developers might appreciate softening the requirement that the mode mask ''affects'' the file access permissions, since it seems access control lists might replace the mode mask to some degree. The wording has been changed to say that it affects the file permission bits, and leaves the details of the behavior of how they affect the file access permissions to the description in POSIX.1 {8}.

4.68 uname — Return system name

4.68.1 Synopsis

```
uname [−amnrsv]
```

4.68.2 Description

By default, the uname utility shall write the operating system name to standard output. When options are specified, symbols representing one or more system characteristics shall be written to the standard output. The format and contents of the symbols are implementation defined. On systems conforming to POSIX.1 {8}, the symbols written shall be those supported by the POSIX.1 {8} *uname*() function.

4.68.3 Options

The uname utility shall conform to the utility argument syntax guidelines described in 2.10.2.

The following options shall be supported by the implementation:

−a Behave as though all of the options −mnrsv were specified.

−m Write the name of the hardware type on which the system is running to standard output.

−n Write the name of this node within an implementation-specified communications network.

−r Write the current release level of the operating system implementation.

−s Write the name of the implementation of the operating system.

−v Write the current version level of this release of the operating system implementation.

If no options are specified, the uname utility shall write the operating system name, as if the −s option had been specified.

4.68.4 Operands

None.

4.68.5 External Influences

4.68.5.1 Standard Input

None.

4.68.5.2 Input Files

None.

4.68.5.3 Environment Variables

The following environment variables shall affect the execution of `uname`:

LANG This variable shall determine the locale to use for the locale categories when both **LC_ALL** and the corresponding environment variable (beginning with **LC_**) do not specify a locale. See 2.6.

LC_ALL This variable shall determine the locale to be used to override any values for locale categories specified by the settings of **LANG** or any environment variables beginning with **LC_**.

LC_CTYPE This variable shall determine the locale for the interpretation of sequences of bytes of text data as characters (e.g., single- versus multibyte characters in arguments).

LC_MESSAGES This variable shall determine the language in which messages should be written.

4.68.5.4 Asynchronous Events

Default.

4.68.6 External Effects

4.68.6.1 Standard Output

By default, the output shall be a single line of the following form:

`"%s\n"`, *<sysname>*

If the `-a` option is specified, the output shall be a single line of the following form:

`"%s %s %s %s %s\n"`, *<sysname>*, *<nodename>*, *<release>*, *<version>*, *<machine>*

Additional implementation-defined symbols may be written; all such symbols shall be written at the end of the line of output before the `<newline>`.

If options are specified to select different combinations of the symbols, only those symbols shall be written, in the order shown above for the `−a` option. If a symbol is not selected for writing, its corresponding trailing `<blank>`s also shall not be written.

4.68.6.2 Standard Error

Used only for diagnostic messages.

4.68.6.3 Output Files

None.

4.68.7 Extended Description

None.

4.68.8 Exit Status

The `uname` utility shall exit with one of the following values:

- 0 The requested information was successfully written.
- >0 An error occurred.

4.68.9 Consequences of Errors

Default.

4.68.10 Rationale. *(This subclause is not a part of P1003.2)*

Examples, Usage

The following command:

```
uname −sr
```

writes the operating system name and release level, separated by one or more `<blank>`s.

Note that any of the symbols could include embedded `<space>`s, which may affect parsing algorithms if multiple options are selected for output.

The node name is typically a name that the system uses to identify itself for intersystem communication addressing.

History of Decisions Made

It was suggested that this utility cannot be used portably, since the format of the symbols is implementation defined. The POSIX.1 {8} working group could not achieve consensus on defining these formats in the underlying *uname*() function and there is no expectation that POSIX.2 would be any more successful. In any event, some applications may still find this historical utility of value. For example, the symbols could be used for system log entries or for comparison with operator or user input.

4.69 `uniq` — Report or filter out repeated lines in a file

4.69.1 Synopsis

`uniq [−c|−d|−u][−f` *fields* `][−s` *chars* `][`*input_file* `[`*output_file* `]]`

Obsolescent Version:

`uniq [−c|−d|−u][−`*n*`][+`*m*`][`*input_file* `[`*output_file* `]]`

4.69.2 Description

The `uniq` utility shall read an input file comparing adjacent lines, and write one copy of each input line on the output. The second and succeeding copies of repeated adjacent input lines shall not be written.

Repeated lines in the input shall not be detected if they are not adjacent.

4.69.3 Options

The `uniq` utility shall conform to the utility argument syntax guidelines described in 2.10.2; the obsolescent version does not, as one of the options begins with + and the −*m* and +*n* options do not have option letters.

The following options shall be supported by the implementation:

`−c` Precede each output line with a count of the number of times the line occurred in the input.

`−d` Suppress the writing of lines that are not repeated in the input.

`−f` *fields* Ignore the first *fields* fields on each input line when doing comparisons, where *fields* shall be a positive decimal integer. A field is the maximal string matched by the basic regular expresssion:

```
[[:blank:]]*[^[:blank:]]*
```

If the *fields* option-argument specifies more fields than appear on an input line, a null string shall be used for comparison.

−s *chars* Ignore the first *chars* characters when doing comparisons, where *chars* shall be a positive decimal integer. If specified in conjunction with the −f option, the first *chars* characters after the first *fields* fields shall be ignored. If the *chars* option-argument specifies more characters than remain on an input line, a null string shall be used for comparison.

−u Suppress the writing of lines that are repeated in the input.

−*n* (Obsolescent.) Equivalent to −f *fields* with *fields* set to *n*.

+*m* (Obsolescent.) Equivalent to −s *chars* with *chars* set to *m*.

4.69.4 Operands

The following operands shall be supported by the implementation:

input_file A pathname of the input file. If the *input_file* operand is not specified, or if the *input_file* is −, the standard input shall be used.

output_file A pathname of the output file. If the *output_file* operand is not specified, the standard output shall be used. The results are unspecified if the file named by *output_file* is the file named by *input_file* .

4.69.5 External Influences

4.69.5.1 Standard Input

The standard input shall be used only if no *input_file* operand is specified or if *input_file* is −. See Input Files.

4.69.5.2 Input Files

The input file shall be a text file.

4.69.5.3 Environment Variables

The following environment variables shall affect the execution of uniq:

LANG This variable shall determine the locale to use for the locale categories when both **LC_ALL** and the corresponding environment variable (beginning with **LC_**) do not specify a locale. See 2.6.

LC_ALL This variable shall determine the locale to be used to override any values for locale categories specified by the settings of **LANG** or any environment variables beginning with **LC_**.

LC_CTYPE This variable shall determine the locale for the interpretation of sequences of bytes of text data as characters (e.g., single- versus multibyte characters in arguments and input files) and which characters constitute a `<blank>` in the current locale.

LC_MESSAGES This variable shall determine the language in which messages should be written.

4.69.5.4 Asynchronous Events

Default.

4.69.6 External Effects

4.69.6.1 Standard Output

The standard output shall be used only if no *output_file* operand is specified. See Output Files.

4.69.6.2 Standard Error

Used only for diagnostic messages.

4.69.6.3 Output Files

If the `-c` option is specified, the output file shall be empty or each line will be of the form:

`"%d %s"`, *<number of duplicates>* , *<line>*

otherwise, the output file will be empty or each line will be of the form:

`"%s"`, *<line>*

4.69.7 Extended Description

None.

4.69.8 Exit Status

The `uniq` utility shall exit with one of the following values:

0 The utility executed successfully.

>0 An error occurred.

4.69.9 Consequences of Errors

Default.

4.69.10 Rationale. *(This subclause is not a part of P1003.2)*

Examples, Usage

Some historical implementations have limited lines to be 1080 bytes in length, which will not meet the implied {LINE_MAX} limit.

The `sort` utility (see 4.58) can be used to cause repeated lines to be adjacent in the input file.

The following input file data (but flushed left) was used for a test series on `uniq`:

```
#01 foo0 bar0 foo1 bar1
#02 bar0 foo1 bar1 foo1
#03 foo0 bar0 foo1 bar1
#04
#05 foo0 bar0 foo1 bar1
#06 foo0 bar0 foo1 bar1
#07 bar0 foo1 bar1 foo0
```

What follows is a series of test invocations of the `uniq` utility that use a mixture of `uniq`'s options against the input file data. These tests verify the meaning of *adjacent* . The `uniq` utility views the input data as a sequence of strings delimited by `\n`. Accordingly, for the *fields* th member of the sequence, `uniq` interprets unique or repreated adjacent lines strictly relative to the *fields* +1th member.

This first example tests the line counting option, comparing each line of the input file data starting from the second field:

```
uniq -c -f 1 uniq_0I.t
  1 #01 foo0 bar0 foo1 bar1
  1 #02 bar0 foo1 bar1 foo0
  1 #03 foo0 bar0 foo1 bar1
  1 #04
  2 #05 foo0 bar0 foo1 bar1
  1 #07 bar0 foo1 bar1 foo0
```

The number `2`, prefixing the fifth line of output, signifies that the `uniq` utility detected a pair of repeated lines. Given the input data, this can only be true when `uniq` is run using the `-f 1` option (which causes `uniq` to ignore the first field on each input line).

The second example tests the option to suppress unique lines, comparing each line of the input file data starting from the second field:

```
uniq -d -f 1 uniq_0I.t
#05 foo0 bar0 foo1 bar1
```

This test suppresses repeated lines, comparing each line of the input file data starting from the second field: