IEEE P1003.2a Draft 8 – December 1991

Copyright © 1991 by the
Institute of Electrical and Electronics Engineers, Inc.
345 East 47th Street
New York, NY 10017, USA
All rights reserved as an unpublished work.

This is an unapproved and unpublished IEEE Standards Draft, subject to change. The publication, distribution, or copying of this draft, as well as all derivative works based on this draft, is expressly prohibited except as set forth below.

Permission is hereby granted for IEEE Standards Committee participants to reproduce this document for purposes of IEEE standardization activities only, and subject to the restrictions contained herein.

Permission is hereby also granted for member bodies and technical committees of ISO and IEC to reproduce this document for purposes of developing a national position, subject to the restrictions contained herein.

Permission is hereby also granted to the preceding entities to make limited copies of this document in an electronic form only for the stated activities.

The following restrictions apply to reproducing or transmitting the document in any form: 1) all copies or portions thereof must identify the document's IEEE project number and draft number, and must be accompanied by this entire notice in a prominent location; 2) no portion of this document may be redistributed in any modified or abridged form without the prior approval of the IEEE Standards Department.

Other entities seeking permission to reproduce this document, or any portion thereof, for standardization or other activities, must contact the IEEE Standards Department for the appropriate license.

Use of information contained in this unapproved draft is at your own risk.

IEEE Standards Department
Copyright and Permissions
445 Hoes Lane, P.O. Box 1331
Piscataway, NJ 08855-1331, USA
+1 (908) 562-3800
+1 (908) 562-1571 [FAX]

Current column : Move to the first nonblank character of the sentence.

5.35.7.1.29 Move forward to beginning of sentence

Synopsis : [*count*])

Move forward to the beginning of a sentence. A *count* shall move forward that many sentences.

Current line : Move to the line containing the beginning of the sentence.

Current column : Move to the first nonblank character of the sentence.

5.35.7.1.30 Move back to preceding paragraph

Synopsis : [*count*] {

Move back to the beginning of the preceding paragraph. A *count* specifies the number of paragraphs to move backward. This command shall be affected by the `paragraph` option; see 5.10.7.5.12.

Current line : Move to the line containing the beginning of the previous paragraph.

Current column : Move to the first nonblank character of the current line.

5.35.7.1.31 Move forward to next paragraph

Synopsis : [*count*] }

Move forward to the beginning of the next paragraph. A *count* specifies the number of paragraphs to move forward. This command shall be affected by the `paragraph` option; see 5.10.7.5.12.

Current line : Move to the line containing the beginning of the next paragraph.

Current column : Move to the first nonblank character of the current line.

5.35.7.1.32 Move to specific column position

Synopsis : [*count*] |

Place the cursor in the column position identified by *count* (if that position exists on the line). If *count* is omitted, it shall default to 1. If the length of the current line is less than *count* , the cursor shall be placed at the end of the current line. If the column position is spanned by a `<tab>` or a wide character, the cursor shall be placed on the character following the *count* -th column position.

Current line : Unchanged.

Current column : Move to the column position represented by *count* .

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

6897 **5.35.7.1.33 Reverse find character**

6898 *Synopsis* : [*count*] `,`

6899 Reverse the last `f`, `F`, `t`, or `T` command, looking the other way in the current line.
6900 A *count* shall be equivalent to repeating the search that many times.

6901 *Current line* : Unchanged.

6902 *Current column* : Move to the first column position of the next character found.

6903 **5.35.7.1.34 Move to first nonblank of previous line**

6904 *Synopsis* : [*count*] –

6905 Move to the first nonblank character in the previous line. A *count* specifies how
6906 many lines to move back.

6907 *Current line* : *line* − *count*

6908 *Current column* : Move to the first nonblank character of the current line or the
6909 last character if the line is a blank line.

6910 **5.35.7.1.35 Repeat**

6911 *Synopsis* : [*count*] `.`

6912 Repeat the last command that changed the buffer. A *count* shall be passed on to
6913 the command being repeated.

6914 *Current line* : Dependent on the results of the execution of the last command that
6915 changed the buffer.

6916 *Current column* : Dependent on the results of the execution of the last command
6917 that changed the buffer.

6918 **5.35.7.1.36 Find regular expression**

6919 *Synopsis* : `/`

6920 Prompt the user to enter a string on the last line on the screen, interpret it as a
6921 regular expression (see 5.10.7.3), and scan forward for the next occurrence of a
6922 matching string. The search shall begin when a `<newline>` or an `<ESC>` is
6923 entered to terminate the pattern; it can be prematurely terminated with an inter-
6924 rupt. 7

6925 When used with an operator to specify an extent of text, the defined region is from
6926 the current cursor position to the beginning of the matched string. Whole lines
6927 can be specified by giving an offset from the matched line (using a closing `/` fol-
6928 lowed by a +*n* or −*n*).

6929 Regular expressions are described in `ex`; see 5.10.7.3.

6930 *Current line* : Move to the line in which the first (or next) regular expression
6931 match occurred.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

Current column : Move to the column of the first character of the matched string.

5.35.7.1.37 Move to first character in line

Synopsis : `0` (zero)

Move to the first character on the current line. (The zero shall not be interpreted as a command when it is preceded by a nonzero digit.)

Current line : Unchanged.

Current column : Column position 1.

5.35.7.1.38 Execute an `ex` command

Synopsis : `:`

Begin an `ex` command. The `:` character, as well as the entered command, shall be displayed on the bottom line. The command shall be executed when the input is terminated by entering a `<newline>` or an `<ESC>`. Typing a `control-V` (or `control-Q`) character shall escape the following character, allowing its literal value to be entered.

NOTE: This special property of `control-V` and `control-Q` is only effective in visual or open modes and in `ex` commands called from visual/open mode with the `:` command.

If the `ex` command causes the screen to be scrolled or causes an escape to the shell, `vi` shall display a message indicating that it is waiting for a `<newline>` character. When a `<newline>` or an `<ESC>` character is entered, the screen shall be refreshed.

Current line : Dependent on the results of the execution of the `ex` command.

Current column : Dependent on the results of the execution of the `ex` command.

5.35.7.1.39 Repeat find

Synopsis : **[***count* **]** `;`

Repeat the last character find using `f`, `F`, `t`, or `T`. A *count* shall move the cursor to (or next to) the *count* -th occurrence of the character.

Current line : Unchanged.

Current column : Move to the column containing the character being searched for. If no matching character is found, it shall be unchanged.

5.35.7.1.40 Shift left

Synopsis : **[***count* **]** `<` **[***motion* **]**

Shift lines left one *shiftwidth* (see 5.10.7.5.20). The command can be followed by a motion command to specify lines. A *count* shall be passed through to the motion command.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

When *motion* is **<**, it shall shift the current line (or *count* lines starting at the current one).

Current line : Unchanged.

Current column : Move to the first nonblank character of the line or the last character if the line is a blank line.

5.35.7.1.41 Shift right

Synopsis : **[** *count* **]** **>** **[** *motion* **]**

Shift lines right one *shiftwidth* (see 5.10.7.5.20). The command can be followed by a motion command to specify lines. A *count* shall be passed through to the motion command.

When *motion* is **>**, it shall shift the current line (or *count* lines starting at the current one).

Empty lines shall not be changed.

Current line : Unchanged.

Current column : Move to the first nonblank character of the line or the last character if the line is a blank line.

5.35.7.1.42 Scan backwards for regular expression

Synopsis : **?**

Scan backwards, the reverse of **/**. See 5.35.7.1.36.

Current line : Move to the line in which the next succeeding regular expression match occurred.

Current column : Move to the column of the first character of the matched string.

5.35.7.1.43 Execute

Synopsis : *@buffer*

Execute each line of the named buffer as one or more **vi** commands (including **ex** commands, as described in 5.35.7.1.38). If the buffer name is **@**, then the last buffer executed shall be used; if there is no last buffer, an error shall occur. The text of a macro may contain an **@** character calling another macro; however, recursively calling the same macro produces undefined behavior. A **vi** error shall terminate all currently executing macros. All changes made during a macro call shall be treated as a unit and can be undone with a single **u** command.

Current line : Dependent on the results of the execution of the **vi** command(s).

Current column : Dependent on the results of the execution of the **vi** command(s).

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

6999 #### 5.35.7.1.44 Reverse case

7000 *Synopsis* : [*count*] ~

7001 Reverse the case of the *count* character(s) beginning at the current cursor posi-
7002 tion. Lowercase alphabetic characters shall be changed to uppercase and upper-
7003 case characters changed to lowercase. This command shall have no effect on
7004 nonalphabetic characters.

7005 *Current line* : Unchanged.

7006 *Current column* : Move to the next column unless it is on the last character of the
7007 line, in which case it shall remain unchanged.

7008 #### 5.35.7.1.45 Append

7009 *Synopsis* : [*count*] a

7010 Enter input mode, appending the entered text after the current cursor position. A
7011 *count* shall cause the inserted text up to the first <newline> to be replicated that 8
7012 many times; if a <newline> appears in the inserted text, only one occurrence of it 8
7013 and any characters following it shall be inserted. For example, if the current line 8
7014 is abc, the command 8

7015 ```
03afoo<newline>bar
```
8

7016 changes that line to 8

7017 ```
afoofoofoo
```
8
7018 ```
barbc
```
8

7019 *Current line* : Unchanged. 7

7020 *Current column* : *column* + 1. 7

7021 #### 5.35.7.1.46 Append at end of line

7022 *Synopsis* : [ *count* ] A

7023 Append *count* copies of the input text at the end of the current line, equivalent to
7024 $[ *count* ] a. See the a command in 5.35.7.1.45.

7025 *Current line* : Unchanged. 8

7026 *Current column* : See 5.35.7.1.45.

7027 #### 5.35.7.1.47 Move backward to preceding word

7028 *Synopsis* : [ *count* ] b

7029 Move the cursor backward to the beginning of a word by repeating the following
7030 algorithm *count* times: If the current position is at the beginning of a word, the 7
7031 current position shall move to the first character of the preceding word. Other-
7032 wise, the current position shall move to the first character of the word at the
7033 current position. If no preceding word exists on the current line, the current posi-
7034 tion shall move to the first character of the last word on the first preceding line

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.
```

that contains a word. For this command, an empty or blank line shall be considered to contain exactly one word.

Current line : Set to the line containing the word selected.

Current column : Set to the first character of the word selected.

5.35.7.1.48 Move backward to preceding bigword

Synopsis : [*count*] B

Move the cursor backward to the beginning of a bigword by repeating the following algorithm *count* times: If the current position is at the beginning of a bigword or the character at the current position cannot be part of a bigword, the current position shall move to the first character of the preceding bigword. Otherwise, the current position shall move to the first character of the bigword at the current position. If no preceding bigword exists on the current line, the current position shall move to the first character of the last bigword on the first preceding line that contains a bigword. For this command, an empty or blank line is considered to contain exactly one bigword.

Current line : Set to the line containing the bigword selected.

Current column : Set to the first character of the bigword selected.

5.35.7.1.49 Change

Synopsis : [*buffer*] [*count*] c *motion*

Delete the specified region of text and enter input mode to replace it with the entered text. If more than part of a single line is affected, the deleted text shall be saved in the numeric buffers. If only part of the current line is affected, then the last character to be deleted shall be marked with a $. A *count* shall be passed through to the motion command.

Current line : The current line and column position are dependent on the *motion* command following the c. For example, cw changes a word, c[[changes from the beginning of the current section, etc.

Current column : See *Current line* , above

5.35.7.1.50 Change to end-of-line

Synopsis : [*buffer*] [*count*] C

Change text from the current position through the end of line (*line* + *count* − 1); equivalent to [*buffer*] [*count*] c$.

Current line : See the c command in 5.35.7.1.49.

Current column : See 5.35.7.1.49.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

5.35.7.1.51 Delete

Synopsis : [*buffer*] [*count*] d *motion*

Delete the specified region of text. If more than part of a line is affected, the text shall be saved in the numeric buffers as well as any named [*buffer*]. A *count* shall be passed through to the motion command.

Current line : The current line and column position are dependent on the *motion* command following the d. For example, dw deletes a word, d$ deletes to the end of the line, etc.

Current column : See *Current line* , above.

5.35.7.1.52 Delete to end-of-line

Synopsis : [*buffer*] [*count*] D

Delete the text from the current position to the end of the current line; equivalent to [*buffer*] [*count*] d$.

Current line : Unchanged.

Current column : Set to maximum of *column* − 1 or 1.

5.35.7.1.53 Move to end of word

Synopsis : [*count*] e

Move the cursor forward to the end of a word, by repeating the following algorithm *count* times: If the current position is the end of a word, the current position shall move to the last character of the following word. Otherwise, the current position shall move to the last character of the word at the current position. If no succeeding word exists on the current line, the current position shall move to the last character of the first word on the next following line that contains a word. For this command, an empty or blank line is considered to contain exactly one word.

Current line : Set to the line containing the word selected.

Current column : Set to the last character of the word selected.

5.35.7.1.54 Move to end of bigword

Synopsis : [*count*] E

Move the cursor forward to the end of a bigword, by repeating the following algorithm *count* times: If the current position is the end of a bigword or the character at that position cannot be part of a bigword, the current position shall move to the last character of the following bigword. Otherwise, the current position shall move to the last character of the bigword at the current position. If no succeeding bigword exists on the current line, the current position shall move to the last character of the first bigword on the next following line that contains a bigword.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

For this command, an empty or blank line is considered to contain exactly one bigword. 7

Current line : Set to the line containing the bigword selected. 7

Current column : Set to the last character of the bigword selected. 7

5.35.7.1.55 Find character in current line (forward)

Synopsis : [*count*] `f` *character*

Scan the rest of the current line for the single character *character* and move the cursor to it if it is found. A *count* shall repeat the find that many times.

Current line : Unchanged.

Current column : Set to the column position containing the character that was scanned for. Unchanged if insufficient characters were found to satisfy the *count* .

5.35.7.1.56 Find character in current line (reverse)

Synopsis : [*count*] `F` *character*

Scan backwards in the current line for the single character *character* , moving the cursor to it if it is found. A *count* shall be equivalent to repeating the search that many times. If the search is unsuccessful, the terminal shall be alerted and the current column position shall remain unchanged.

Current line : Unchanged.

Current column : Set to the last character found moving backwards.

5.35.7.1.57 Move to line

Synopsis : [*count*] `G`

Move the cursor to line *count* , or to the last line of the editing buffer if *count* is not specified.

Current line : *count* , if specified; otherwise, the last line.

Current column : Move to the first nonblank character of the current line or the last character if the line is a blank line.

5.35.7.1.58 Move to top of screen

Synopsis : [*count*] `H`

Move the cursor to the line (*count* − 1) lines from the top of the current window (i.e., the *count* -th line, one-based, currently displayed).

Current line : *count* on the screen, as described above.

Current column : Move to the first nonblank character of the current line or the last character if the line is a blank line.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

5.35.7.1.59 Insert before cursor

Synopsis : [*count*] i

Enter input mode, inserting the entered text before the cursor. (See also the a command in 5.35.7.1.45.) A *count* shall cause the inserted text up to the first <newline> to be replicated that many times; if a <newline> appears in the inserted text, only one occurrence of it and any characters following it shall be inserted.

Current line : Unchanged.

Current column : Unchanged.

5.35.7.1.60 Insert at beginning of line

Synopsis : [*count*] I

Enter input mode at the beginning of a line. This command shall behave identically to the ^[*count*]i command. See 5.35.7.1.59.

Current line : Unchanged.

Current column : Move to the first nonblank character of the current line or the last character if the line is a blank line.

5.35.7.1.61 Join

Synopsis : [*count*] J

Join the current line with the next one, supplying appropriate spacing (in the POSIX Locale): one <space> between words, two <space>s after a period, and no <space>s at all when the last character of the first line is a <blank> or when the first character of the next line is). In the case of lines ending with <blank>s, the <blanks> shall be retained, no spaces shall be added, and the lines shall be joined together. A *count* shall cause that many lines (minimum 2) to be joined, rather than 2. A count of 1 shall be treated as 2.

Current line : Unchanged.

Current column : Move to the character after the last character of the original line.

5.35.7.1.62 Move to bottom of screen

Synopsis : [*count*] L

Move the cursor to the first nonblank character of the last line on the screen. A *count* shall move to that line counting from the bottom. When used with an operator, whole lines shall be affected.

Current line : *last line* − *count*

Current column : Move to the first nonblank character of the current line or the last character if the line is a blank line.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

5.35.7.1.63 Mark position

Synopsis : `m` *letter*

Mark the current position of the cursor with a single POSIX Locale lowercase letter *letter*. The exact position is referred to by `` `letter ``; the line is referred to by `'letter`.

Current line : Unchanged.

Current column : Unchanged.

5.35.7.1.64 Move to middle of screen

Synopsis : `M`

Move the cursor to the middle line on the screen, at the first nonblank position on the line.

Current line : Move to a line approximately in the middle of the display window.

Current column : Move to the first nonblank character of the current line or the last character if the line is a blank line.

5.35.7.1.65 Repeat regular-expression find (forward)

Synopsis : `n`

Repeat the last `/` or `?` scanning command.

Current line : Set to the line containing the character string found by the scan. Unchanged if no match was found.

Current column : Move to the first character of the character string found by the scan. Unchanged if no match was found.

5.35.7.1.66 Repeat regular-expression find (reverse)

Synopsis : `N`

Scan for the next match of the last pattern given to `/` or `?`, but in the reverse direction; this is the reverse of `n`.

Current line : Move to the matched line if a match is found or unchanged if no match is found.

Current column : Move to the first column position of the matched string or unchanged if no match is found.

5.35.7.1.67 Insert empty line below

Synopsis : `o`

Open a line below the current line and enter input mode.

Current line : The newly-created line, (*line* +1).

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

Current column : If the editor option `autoindent` is not set, move to the first column; otherwise, as in the description of `autoindent` in `ex` (see 5.10.7.5.1).

5.35.7.1.68 Insert empty line above

Synopsis : `O`

Open a new line above the current line and enter input mode.

Current line : Unchanged.

Current column : If the editor option `autoindent` is not set, move to the first column; otherwise, as described in the description of `autoindent` in `ex`.

5.35.7.1.69 Put from buffer following

Synopsis : [*buffer*] `p` 7

Insert text from buffer *buffer* following the current column or current line, as described for the `P` command (see 5.35.7.1.70). If *buffer* is omitted, the unnamed buffer shall be used. 7

Current line : (*Current line* +1) if the buffer contains whole lines; otherwise, unchanged.

Current column : First nonblank character of the inserted text if the buffer contained whole lines; otherwise, the last character of the inserted text.

5.35.7.1.70 Put from buffer before

Synopsis : [*buffer*] `P`

Put the last deleted text back before/above the cursor. The text shall go back as whole lines above the cursor if it was deleted as whole lines. Otherwise, the text shall be inserted just before the cursor.

The command can be preceded by a named buffer specification ("*x*), to retrieve the contents of the buffer.

Current line : Unchanged.

Current column : Move to the last column position of the inserted characters. If the buffer contains whole lines, the current column shall be the first nonblank character of the inserted characters.

5.35.7.1.71 Enter `ex` mode

Synopsis : `Q`

Quit from `vi` and enter `ex` command mode.

Current line : Unchanged.

Current column : Unchanged.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

7240 **5.35.7.1.72 Replace character**

7241 *Synopsis* : [*count*] r *character*

7242 Replace a character on the screen with the character entered. If *count* is
7243 specified, the single character entered shall replace the current character and
7244 each of the next *count* − 1 characters in the line. (For example, 7rx changes the
7245 next seven characters to be xxxxxxx). Unlike the R command (see 5.35.7.1.73),
7246 entering a <newline> shall replace the character with a <newline>; however,
7247 when used with *count* , the next *count* characters in the line shall be replaced by a
7248 single <newline>.

7249 *Current line* : Unchanged unless the replacement character is a <newline>, in
7250 which case the current line shall be incremented by 1.

7251 *Current column* : Set to the last column position occupied by the replacement
7252 character, unless the replacement character is a <newline>, in which case the
7253 current column position shall be 1.

7254 **5.35.7.1.73 Replace characters**

7255 *Synopsis* : R

7256 Replace characters on the screen with characters entered. If the end of the exist-
7257 ing line is encountered, it shall be as if insert mode was entered at that point. If a
7258 <newline> is entered before the end of the existing line, it shall be entered into
7259 the editing buffer as if it was inserted, and replacement shall continue on the
7260 newly created line. No other line but the one in which the R command was given
7261 shall be affected.

7262 *Current line* : Set to the line at the end of the replaced text.

7263 *Current column* : Set to the end of the replaced text, if text was replaced. If no 7
7264 text was replaced, set to the column position of the character after which text 7
7265 would have been replaced if that character is on the current line; otherwise, 1. 7

7266 **5.35.7.1.74 Substitute character**

7267 *Synopsis* : [*buffer*] [*count*] s 8

7268 Substitute *count* characters in the current line starting with the current column
7269 position; equivalent to [*buffer*] [*count*] c<space>. 8

7270 *Current line* : Unchanged.

7271 *Current column* : Unchanged.

7272 **5.35.7.1.75 Substitute lines**

7273 *Synopsis* : [*buffer*] [*count*] S 8

7274 Change whole lines (same as cc). A *count* shall change that many lines; *count*
7275 lines shall be deleted and vi shall enter input mode.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

Current line : Unchanged.

Current column : Set to column position 1 or to the position indicated by the previous line if `autoindent` is set.

5.35.7.1.76 Move cursor to before character (forward)

Synopsis : [*count*] `t` *character*

Move the cursor forward within the current line to the character position just before a subsequent occurrence of *character* . A *count* shall place the cursor just before the *count* -th occurrence of the character when searching the line forwards. If the search is unsuccessful, the terminal shall be alerted and the cursor position shall remain unchanged.

Current line : Unchanged.

Current column : Move to the position before an occurrence of *character* following *column* (noninclusive).

5.35.7.1.77 Move cursor to after character (reverse)

Synopsis : [*count*] `T` *character*

Scan backwards in the current line for the single character *character* and if found, place the cursor just after that character. A *count* shall place the cursor just after the *count* -th occurrence of the character when searching the line backwards. If *count* -th occurrences of the character do not exist, the terminal shall be alerted and the current column position shall remain unchanged.

Current line : Unchanged.

Current column : Set to the column after the scanned character. Unchanged if the character was not found.

5.35.7.1.78 Undo

Synopsis : `u`

Reverse the last change made to the current buffer. If repeated, the command shall alternate between these two states, thus is its own inverse. When used after an insert that inserted text on more than one line, the lines shall be saved in the numeric named buffers.

Current line : Move to the position of the first line changed, if the reversal affects only one line or represents an addition or change; otherwise, move to the line preceding the deleted text.

Current column : Move to the first nonblank character on the updated current line.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

7310 #### 5.35.7.1.79 Undo current line

7311 *Synopsis* : `U`

7312 Restore the current line to its state before the cursor was last moved to it.

7313 *Current line* : Unchanged.

7314 *Current column* : Set to column position 1 or to the position indicated by the pre-
7315 vious line if `autoindent` is set.

7316 #### 5.35.7.1.80 Move to beginning of word

7317 *Synopsis* : [*count*] `w`

7318 Move the cursor forward to the beginning of a word by repeating the following
7319 algorithm *count* times: If the current position is at the beginning of a word, the 7
7320 current position shall move to the first character of the next word. If no subse-
7321 quent word exists on the current line, the current position shall move to the first
7322 character of the first word on the first following line that contains a word.

7323 For this command, an empty or blank line is considered to contain exactly one 7
7324 word. 7

7325 *Current line* : Set to the line containing the word selected. 7

7326 *Current column* : Set to the first character of the word selected. 7

7327 #### 5.35.7.1.81 Move to beginning of bigword

7328 *Synopsis* : [*count*] `W`

7329 Move the cursor forward to the beginning of a bigword by repeating the following
7330 algorithm *count* times: If the current position is within a bigword or the character
7331 at that position cannot be part of a bigword, the current position shall move to the
7332 first character of the next bigword. If no subsequent bigword exists on the
7333 current line, the current position shall move to the first character of the first big-
7334 word on the first following line that contains a bigword. For this command, an 7
7335 empty or blank line is considered to contain exactly one bigword. 7

7336 *Current line* : Set to the line containing the bigword selected.

7337 *Current column* : Set to the first character of the bigword selected.

7338 #### 5.35.7.1.82 Delete character at cursor

7339 *Synopsis* : [*buffer*] [*count*] `x` 8

7340 Delete *count* characters in the current line starting with the current column posi-
7341 tion; equivalent to [*buffer*] [*count*] `dl`. If the number of characters to be deleted 8
7342 is greater than or equal to the number of characters to the end of the line, delete
7343 all of the characters from the current position to the end of the line and move the
7344 cursor to the new last character on the line.

7345 *Current line* : Unchanged.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

Current column : Set to the greater of (*current column* − the width of the *count* deleted characters) or 1.

5.35.7.1.83 Delete character before cursor

Synopsis : [*buffer*] [*count*] `X`

Delete the character before the cursor, equivalent to [*buffer*] [*count*] `dh`. A *count* shall repeat the effect, but only characters on the current line shall be deleted.

Current line : Unchanged.

Current column : Set to the greater of (*current column* − the width of the *count* deleted characters) or 1.

5.35.7.1.84 Yank

Synopsis : [*buffer*] [*count*] `y` *motion*

Copy (''yank'') the area of text specified by *count* and *motion* into the unnamed buffer, as well as into any named buffer specified by *buffer* .

Current line : Unchanged.

Current column : Unchanged.

5.35.7.1.85 Yank current line

Synopsis : [*buffer*] [*count*] `Y`

Place (yank) a *count* copies of the current line, equivalent to a [*buffer*] [*count*] `yy` command; see 5.35.7.1.84.

Current line : Unchanged.

Current column : Unchanged.

5.35.7.1.86 Redraw window

Synopsis : [*count1*] `z` [*count2*] *character*

Redraw the screen with a window *count2* lines long containing line *count1* placed as specified by *character* : `<newline>` specifies the top of the screen, `.` specifies the center of the screen, and − specifies the bottom of the screen. If *count1* is not specified, it shall default to the current line; if *count2* is not specified, it shall default to *window* .

Current line : *count1* , if specified; otherwise, unchanged.

Current column : Move to the first nonblank character of the current line or the first character if the line is a blank line.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

5.35.7.1.87 Exit

Synopsis : `ZZ`

Exits the editor, writing out the buffer if it was changed since the last write to any file. This command shall behave identically to the `ex` command `xit`; see 5.10.7.2.38.

5.35.8 Exit Status

The `vi` utility shall exit with one of the following values:

0 Successful completion.

>0 An error occurred.

5.35.9 Consequences of Errors

Default.

5.35.10 Rationale. *(This subclause is not a part of P1003.2a)*

Usage, Examples

The following table is a condensed version of information contained in the normative text. It is presented here to facilitate the review for accuracy of the `vi` commands and the editor options that affect those commands.

`vi` Command	**Editor Option**	**Description**
`control-B`	`window`	Determines screen size for paging.
`control-D`	`scroll`	Determines number of lines to be scrolled.
`control-F`	`window`	Determines screen size for paging.
`control-T`	`shiftwidth`	Move cursor forward shiftwidth positions.
`control-U`	`scroll`	Determines number of lines to be scrolled.
`{ }`	`paragraphs`	Defines additional paragraph boundaries for the `{` and `}` commands.
`[[ ]]`	`sections`	Defines additional section boundaries for the `[[` and `]]` commands.
`/`	`ignorecase`	Characters that have upper- and lowercase representations shall have those representations considered as equivalent for purposes of regular expression comparison.
	`magic`	When set, the characters `^ $ . * [ ~` have special meaning in regular expressions. When unset, only characters `^ $` have special

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

		meaning in regular expressions.
<	shiftwidth	Determines the number of character positions to be shifted.
>	shiftwidth	Determines the number of character positions to be shifted.
?	ignorecase	Characters that have upper- and lowercase representations shall have those representations considered as equivalent for purposes of regular expression comparison.
	magic	When set, the characters ^ $. * [~ have special meaning in regular expressions. When unset, only characters ^ $ have special meaning in regular expressions.
O, o	autoindent	Starting indentation determined by the line on which the command is given.
S	autoindent	Starting indentation determined by the line being changed.
ZZ	readonly	Shall not allow a write to a file.
z	window	Redraw window with the number of lines equal to the default set by window.

The control-L and control-R commands differ in their treatment of deleted ‘‘@’’lines. The former always redisplays the screen and does not affect the status of any @ line; the latter redisplays only when needed to process the deleted @ lines.

When executing an individual ex command by entering :, it is not possible to enter a <newline> as part of the command because it is considered the end of the command. As explained in 5.10.7.4, a control-M preceded by a control-V (or control-Q) escape character in a regular expression substitution is mapped into a <newline>. A different approach is to enter ex command mode by using the vi Q command (and later resuming visual mode with the ex ‘vi’’command). In ex command mode, the single-line limitation does not exist. So, for example, the following is valid:

```
Q
s/break here/break\
here/
vi
```

The uses described for control-V can also be accomplished with control-Q, which is useful on terminals that use control-V for the down-arrow function. However, most historical implementations use control-Q for the *termios* START character, so the editor will generally not receive the control-Q unless stty –ixon mode is set. Any of the command characters described in this standard can be made ineffective by their selection as *termios* control characters, using the stty utility or other methods described in POSIX .1 {8}.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

History of Decisions Made

Historically the `control-B` command skips two lines between each pair of pages it displays from a file. The working group viewed this as a bug and decided to go along with how the command was documented (as overlapping, not skipping, two lines) instead of standardizing the historical implementation.

See the Rationale for the `ex` utility for more information on `vi`.

A ‘‘restricted editor’’ (both the historical `red` utility and modifications to `vi`) were considered and rejected for inclusion. Neither option provided the level of security that many users might expect.

The `[[`, `]]`, `(`, `)`, `{`, and `}` commands are all affected by ‘‘section boundaries,’’ but in current implementations not all of the commands recognize the same section boundaries. This is considered to be a bug rather than a feature and a unique section-boundary algorithm was not described for each command.

The `e` and `E` commands described here differ slightly from some historical implementations in that an empty or blank line is described as containing exactly one word or bigword, just as for `b`, `B`, `w`, and `W`. On some systems, `E` command skips over empty/blank lines. The working group felt that a consistent definition of bigword between the `E` command and the others was sufficient justification to change one so that they all treat empty/blank lines the same way.

The `=` (reindent) command was omitted because it was LISP language-specific. (See the `ex` Rationale for the reasons LISP support was omitted.)

The text in Standard Output reflects the usage of the verb ‘‘display’’ in this clause; some `vi` implementations actually use standard output to write to the terminal, but POSIX.2 does not require that to be the case.

The action taken for signals other than SIGINT, SIGCONT, and SIGHUP is unspecified because some implementations attempt to save the editing buffer in a useful state when other signals are received.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

5.36 who — Display who is on the system

5.36.1 Synopsis

```
who [-mTu]
```

5.36.2 Description

The who utility shall list various pieces of information about accessible users. The domain of accessibility is implementation defined.

The default output shall contain at least the following information for accessible users, in an unspecified format: the user's login name, terminal name, and time at which the user logged in.

5.36.3 Options

The who utility shall conform to the utility argument syntax guidelines described in 2.10.2.

The following options shall be supported by the implementation:

-m Output only information about the current terminal.

-T Show the state of each terminal, as described in 5.36.6.1.

-u Output each displayed user's ''idle time'' in addition to any other information. The idle time is the time since any activity occurred on the user's terminal. The method of determining this is unspecified. 8

5.36.4 Operands

None.

5.36.5 External Influences

5.36.5.1 Standard Input

None.

5.36.5.2 Input Files

None.

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.

7506 #### 5.36.5.3 Environment Variables

7507 The following environment variables shall affect the execution of `who`:

7508 **LANG** This variable shall determine the locale to use for the
7509 locale categories when both **LC_ALL** and the correspond-
7510 ing environment variable (beginning with **LC_**) do not
7511 specify a locale. See 2.6.

7512 **LC_ALL** This variable shall determine the locale to be used to over-
7513 ride any values for locale categories specified by the set-
7514 tings of **LANG** or any environment variables beginning
7515 with **LC_**.

7516 **LC_CTYPE** This variable shall determine the locale for the interpreta-
7517 tion of sequences of bytes of text data as characters (e.g.,
7518 single- versus multibyte characters in arguments).

7519 **LC_TIME** This variable shall determine the format and contents of
7520 the date and time strings.

7521 **LC_MESSAGES** This variable shall determine the language in which mes-
7522 sages should be written.

7523 #### 5.36.5.4 Asynchronous Events

7524 Default.

7525 ### 5.36.6 External Effects

7526 #### 5.36.6.1 Standard Output

7527 The `who` utility writes its default information to the standard output in an
7528 implementation-defined format, subject only to the requirement of containing the
7529 information described above.

7530 The following format shall be used for the `-T` option:

7531 `"%s %c %s %s\n"`, *<user name>* , *<terminal state>* ,
7532 *<terminal name>* , *<time of login>*

7533 where *<terminal state>* is one of the following characters:

7534 `+` The terminal allows write access to other users.

7535 `-` The terminal denies write access to other users.

7536 `?` The terminal write-access state cannot be determined.

7537 In the POSIX Locale, the *<time of login>* shall be equivalent in format to the out-
7538 put of:

7539 `date +"%b %e %H:%M"`

Copyright © 1991 IEEE. All rights reserved.
This is an unapproved IEEE Standards Draft, subject to change.